How to delete material revision level in SAP




The SAP revision levels are typically used to identify that smaller changes to the material have been done like updating specifications, updating drawing information (but no changes that would change the form of the product). A revision level is set for the material at client level, it's shown in almost all the views of the material master right under the material number. The revision level is available in the BOM, MD04, PR, PO and SA however the stock is not segregated by revision level so in MMBE you will not see this revision level, nor will the stock be separated by revision level.


A material can indeed have multiple revision levels assigned mostly in increasing sequence. Only one revision level can be the active.


Here is the instruction how it possible to delete material revision level from change or delete change permanently:

1. Transaction CCUNDO - undo the changes against change number to be





deleted.





2. Transaction CC12 - delete the revision level for material.






elete C revision level.

Save.

3. Transaction CC02 - delete the object management record for material.



	nge i	Master: Cl	hang	ge Header			
🗦 🔊 Object Ty	ypes	<u></u> ∆ Objects	&	Alternative Dates	👿 👫 [> 🛅 🍽	N 🕞
nange number	/	50000004068	9	THE PERSON NAMED IN	Name and Address of the Owner, where	SEC SOLD]
			Ch	ange Master Without	Release Key	,	_
Description							
Valid From		09.09.9999	₽Ţ				
Authorization group	0		ت				
Reason for Change	-	Contract Contract	-	or the State Land			
Reason for Change							
Status Information							
Change no. status	١	1 Active					
✓ Usage							
Deletion Flag	-						
User Status		CRT				Status Mgm	t
Administrative Data							
Created On		02.03.2017 (Create	d by	Mires		
			Change	ed by			
Changed On							
Changed On	▼ « ⊑			(វាម៉ារាវា(ភាគ	@ =		
Changed On	V « 4	1 @ @ 😡 😑		ាសិសិសិស]⊽⊡	② <u>•</u>		
	4	1 @ @ 😡 😑			② 및		
Changed On Change Change I	4	☑ 🐼 😡 🗎 Material: Ove	. M M		② !!		
Changed On Change Change I Sobject Types	4 Master:	Material: Ove	erview Dates	,	② ➡		
Changed On Change Change I Sobject Types	4 Master:	Material: Ove	erview	the from the field	② 및		
Changed On Change Change I Sobject Types	4 Master:	Material: Ove	erview	the from the field	② ➡		
Changed On Change Change I Change Change I Change number Objects Document	4 Master:	Material: Ove S Alternative Change Maste	Dates	the from the field	② 및		
Changed On Change Change I Change Change I Change number Objects Document	4 Master:	Material: Ove S Alternative Change Maste	Dates	it Release Key	② 및		
Changed On Change Change I Change Change I Change number Objects Document 3	4 Master:	Material: Ove S Alternative Change Maste	Dates	it Release Key	② 및		
Changed On Change Change I Change Change I Object Types Change number Objects Document The property of t	4 Master: 500000040 Materia	Material: Ove S Alternative Change Maste	Dates T Withou	order BOM Doc. Struc. Material description	C Valid From	Alternative date	Lock
Changed On Change Change I Change Change I Objects Types Change number Objects Document The property of	4 Master: 500000040 Materia RevLev	Material: Ove Material: Ove Change Maste	Dates T Withou	order BOM Doc. Struc. Material description	C Valid From	Alternative date	
Changed On Change Change I Object Types Change number Objects Document 2 terial 21901149 21901220	4 Master: 500000040 Materia RevLev C A	Material: Ove Material: Ove Change Maste	Dates T Withou	order BOM Doc. Struc. Material description	C Valid From 09.09.9999	Alternative date	
Changed On Change Change I Change Change I Objects Document Objects Document 2 terial 21901149 21901220 21901221	4 Master: 500000040 Materia RevLev	Material: Ove Material: Ove Change Maste	Dates T Withou	order BOM Doc. Struc. Material description	C Valid From	Alternative date	

Also possible to delete all material revision levels useing Functional Module: FM: REVISION_LEVEL_DELETE