


# Delete Handling Unit (HU) via FM



There is a possibility to change HU data via Functional module. Go through the instruction below:

1) Go to Transaction **SE37**

2) Enter FM: **V51S\_HU\_UPDATE\_DB** and press **F8**



3) Select necessary action (Insert, Update, Delete) on appropriate level (Header or Item)

Test Function Module: Initial Screen

Debugging Test data directory

Test for function group V51S  
 Function module V51S\_HU\_UPDATE\_DB  
 Uppercase/Lowercase

Import parameters	Value
IT_HDR_INSERT	0 Entries
IT_HDR_UPDATE	0 Entries
IT_HDR_DELETE	0 Entries
IT_ITM_INSERT	0 Entries
IT_ITM_UPDATE	0 Entries
IT_ITM_DELETE	0 Entries
IT_HIS_INSERT	0 Entries
IT_HIS_UPDATE	0 Entries
IT_HIS_DELETE	0 Entries

4) Enter key values and Back to previous screen

Structure Editor: Change IT\_ITM\_DELETE from Entry 1

0 Entries

MAN	VENUM	VEPOS	V	VBELN	POSNR	V	UNVEL	VEMNG	VEMNG_FLO	VEM	ALT	VEANZ	K	MATNR	CHARG	WERK	LGOR	CT
100	0006040731	000099			000000			0,000	0,0000000000000000E+00			0						

Test Function Module: Initial Screen

Debugging Test data directory

Test for function group V51S  
Function module V51S\_HU\_UPDATE\_DB  
Uppercase/Lowercase

Import parameters	Value
IT_HDR_INSERT	0 Entries
IT_HDR_UPDATE	0 Entries
IT_HDR_DELETE	0 Entries
IT_ITM_INSERT	0 Entries
IT_ITM_UPDATE	0 Entries
IT_ITM_DELETE	1 Entry
IT_HIS_INSERT	0 Entries
IT_HIS_UPDATE	0 Entries
IT_HIS_DELETE	0 Entries

5) Save

6) Check result in tables **VEKP, VEPO**